

This notice of alterations provides changes that must be made to the 16th edition of FieldMate Versatile Device Management Wizard R3.03 (IM 01R01A01-01EN).

S Calibration Support

■ Support with PM100 External pressure sensor

When PM100 External pressure sensor is connected to the CA700 pressure calibrator, the calibration setting items related to the external pressure sensor are displayed at the bottom of the screen in Figure S-2-5 Setting dialog. This items need to set if using External pressure sensor for calibration work,

T BT200 Tablet

■ Collaboration with Device Maintenance Information

Information of the BRAIN device connected with the BT200 tablet is automatically stored as FieldMate Device Maintenance Information. The stored information can be output in arbitrary format as well as all parameters and used Compare parameters etc.

*Refer to “H-2-3 All Parameters/Adjustment Parameters” and “H-2-6 Parameter Comparison” in IM for FieldMate about all parameters and Compare parameters.