

Notice of Alterations

Model LL1100
PC-based Parameters Setting Tool
Model LL1200
PC-based Custom Computation Building Tool

IM 05G01A01-01E-S01

YOKOGAWA
Yokogawa Electric Corporation

2nd Edition: Feb. 2012

- The media for LL1100/LL1200 were changed into CD from the 3.5-inch floppy disk. For the confirmation of the package contents and the setup method, see this Notice of Alterations.
- The user's manuals of LL1100/LL1200 on CD describe the usage with RS-232C serial communication. For the LL1100/LL1200 supporting USB, see this Notice of Alterations for the following contents which are related to USB.

Contents related USB: ■ Confirmation of the Package Contents
■ Operating Environment and Wiring Specifications
■ Setup
Installing USB Converter Driver Software
Installing LL1100/LL1200
■ Connecting Controller to Personal Computer

- The applicable OS of the LL1100/LL1200 tool changed. For confirmation of the operating environment specifications, see this Notice of Alterations.

For the start-up of LL1100/LL1200 and the operation method, see the user's manual.
LL1100 PC-based Parameters Setting Tool: IM 5G1A01-01E
LL1200 PC-based Custom Computation Building Tool: IM 5G1A11-01E
The release number of the LL1100/LL1200 tool is printed on the product CD.

Checking the Contents of the Package

Model and Suffix Code

Model	Suffix code	Description
LL1100		PC-based Parameters Setting Tool
LL1200		PC-based Custom Computation Building Tool
	-U10	Model for use with IBM PC/AT compatible machine (common to English and Japanese version), USB interface

-U10 CD (1 disk):
LL1100 or LL1200/USB converter driver software (1 disk)
Dedicated adapter (for USB interface) and dedicated cable (for USB interface):
For connecting a personal computer to optical communication interface on the front of the US1000 controller (1 set)
User's Manual (LL1100; 1 copy, LL1200; 3 copies)

Note

While the CD is being accessed, do not remove the CD from the CD-ROM drive, cut the power to the PC, or reset the computer.

Operating Environment Specifications

PC

Applicable OS: Windows XP (Home Edition/Professional (32-bit version)
Windows Vista Business (with Service Pack 1) (32-bit version)
Windows 7 Professional (32-bit/64-bit versions)
.NET Framework 3.5 installed.

Recommended CPUs: Pentium Processor 300 MHz or higher
(3.0 GHz or higher in Windows Vista Business/Windows 7 Professional)

Recommended Main Memory:
Windows XP (Home Edition/Professional); 128 MB or more
Windows Vista Business/Windows 7 Professional; 2 GB or more

Hard disk space:
Memory space required to store the tool's programs; 5 MB for LL1100 and 9 MB for LL1200
Memory space required to store the parameter data; 2 MB minimum
Memory space required to store the driver for USBSerial converter; 1 MB
Display: 800 x 600 pixels or more
Color: 256 or more colors

USB communication port: One channel (COM1 to COM16), with SeriesA connector, compliant with USB Specification Rev1.1.

Network: 10BASE-T/100BASE-TX (required for Ethernet communication)

CD-ROM drive: One (required for installation)

Printer: Paper size; Letter or A4 (required for printing)

Dedicated Adapter (for USB interface)

Communication method:

Controller; optical, contactless, bidirectional serial communication
Personal computer; compliant with USB Specification Rev1.1

Power supply: Supplied from USB bus power (no internal battery)

Input rating; 4.4 to 5.25 V DC, 100 mA (including a dedicated cable)
* No plug for external power supply, no power switch


Ambient temperature range: 0 to 50°C

Ambient humidity range: 20 to 90% RH (no condensation)

Transport and storage conditions: -20 to 65°C, 10 to 90%RH (no condensation)
Dust- and water-proof construction: Not applied.

Standard: CE Marking (EMC only) to be approved

Unit: mm



The dedicated adapter and the dedicated cable are not waterproof. Do not use them in locations that are likely to be exposed to splashes of water or other liquids.


Dedicated Cable (for USB interface)

Built-in USB-Serial converter

Personal computer side: USB SeriesA plug

Adapter side: RJ45 (8-pin) plug

Cable length: Approx. 2.7 m



Unit: mm

Note: The dedicated cable for USB interface is for the dedicated adapter for USB interface. It can not be used for the dedicated adapter for serial interface.

Installing USB Converter Driver Software



- Logon in Windows XP:
- Log on using the user name of Administrators group.
- The program does not start normally if the user name not belonging to the Administrators group is used for logging on.
- In Windows Vista/Windows 7, install USB converter driver software as an administrator.
- Avoid entering just the drive as the installation location, such as C:\. Enter the full directory path.
- Before installing USB converter driver software, quit all running applications.
- When reinstalling USB converter driver software, uninstall the installed USB converter driver software first, and then reinstall USB converter driver software.

Installing USB Converter Driver Software in Windows Vista/Windows 7

Operating procedures and screens in Windows Vista.

- Start Windows.

- Insert the CD of LL1100 or LL1200 into the CD-ROM drive. The start-up screen appears automatically.




Note: If the start-up screen does not appear automatically and the AutoPlay screen appears, click Run startup.exe to display the start-up screen.




- Click USB Driver Installation.




- The User Account Control screen appears. Click Continue.




- Installshield Wizard screen appears. Click Next.




- Click Install.




- The Windows Security screen appears. Click Install. (USB device driver)



- The Windows Security screen appears. Click Install. (COM port driver)



- When installation is complete, the Finish dialog box appears. Click Finish.




The dialog box closes. You have completed installing the driver software in Windows Vista.

When you connect the dedicated cable to a USB port on your computer, the driver becomes available automatically.

For installation of USB converter driver software in Windows 7, follow the message given in each dialog box.

Installing USB Converter Driver Software in Windows XP

- Start Windows.
- Insert the CD of LL1100/LL1200 into the CD-ROM drive. The start-up screen appears automatically.
- Click USB Driver Installation.
- Installshield Wizard screen appears. Click Next.
- Click Install.
- A message appears to warn that the software you are installing has not passed Windows Logo testing. Click Continue Anyway.
- The same warning message appears. Click Continue Anyway.
- When installation is complete, the Finish dialog box appears. Click Finish.
- Connect the connector of the dedicated cable to the USB communication port of a personal computer. The Found New Hardware Wizard appears automatically. Select No, not this time. Click Next.



- Select Install the software automatically (Recommended). Click Next.
- A message appears to warn that the software you are installing has not passed Windows Logo testing. Click Continue Anyway.
- Copying of the USB device driver for the dedicated cable begins. When installation is completed, a confirmation message appears. Click Finish.
- Installation of the virtual COM port driver begins continuously. Select No, not this time. Click Next.
- Select Install the software automatically (Recommended). Click Next.

15. A message appears to warn that the software you are installing has not passed Windows Logo testing. Click **Continue Anyway**.

16. Copying of the virtual COM port driver begins. When installation is completed, a confirmation message appears. Click **Finish**.

You have completed installing the driver software in Windows XP.

■ Verifying Installation

Operating procedures and screens in Windows Vista


1. From the **Start** menu of Windows, select **Control Panel > Device manager**.

Note 1: From the **Start** menu of Windows, select **Control Panel > System and Maintenance > Device manager** if the control panel's display method is "Control Panel Home."


Note 2: In Windows XP, from the **Start** menu of Windows, select **Control Panel > System > Hardware > Device manager** and verify the steps 3 and 4."

2. In Windows Vista, the User Account Control screen appears. Click **Continue**.

3. Verify that the virtual COM port driver (1) "YOKOGAWA USB Serial Port (COMn)" is displayed under "Ports (COM & LPT)" as COM port and the USB device driver (2) "YOKOGAWA USB Serial Converter A1053UR" is displayed under "Universal Serial Bus controllers."



4. The COM port number assigned to the dedicated cable can be verified by the port number displayed in (1) "YOKOGAWA USB Serial Port (COMn)" of Device Manager (see the step 3). To change the COM port number, double-click (1), select Port Settings tab of Properties screen and click **Advanced**. Change the COM port number in the Advanced Settings for COMn screen.



■ Uninstalling USB Converter Driver Software

Operating procedures in Windows Vista



Unplug the dedicated cable if it is connected to a personal computer.

1. Unplug the dedicated cable if it is connected to a personal computer.

2. From the **Start** menu of Windows, select **Control Panel > Programs and Features**.


Note 1: From the **Start** menu of Windows, select **Control Panel > Uninstall a program** if the control panel's display method is "Control Panel Home."

Note2: In Windows XP, from the **Start** menu of Windows, select **Control Panel > Add or Remove Programs** and uninstall the driver software."

3. Select **YOKOGAWA A1053UR Installer** and click **Uninstall**.

4. In Windows Vista, the **User Account Control** screen appears. Click **Continue**.

5. The Confirm Uninstall screen appears. Click **Yes**.



6. The Uninstall Complete screen appears. Click **Finish**.

You have completed uninstalling the driver software.

Installing LL1100/LL1200 Tool



- Logon in Windows XP:
 - Log on using the user name of Administrators group.
 - The program does not start normally if the user name not belonging to the Administrators group is used for logging on.
- In Windows Vista/Windows 7, install the software as an administrator.
- In Windows Vista/Windows 7, do not set LL1100/LL1200 user file save directory in Program Files folder. The LL1100/LL1200 will not work properly. Also if LL1100/LL1200 user file save directory is set in Program Files folder on Windows XP personal computer, do not upgrade its OS to Windows Vista/Windows 7.
- Before installing LL1100/LL1200 Setting Software, quit all running applications.
- Avoid entering just the drive as the installation location, such as C:\. Enter the full directory path.
- When .NET Framework 3.5 SP1 is not installed on Windows XP/Windows Vista/Windows 7 personal computer, .NET Framework 3.5 SP1 is installed to start LL1100/LL1200.
- When reinstalling LL1100/LL1200, uninstall the installed LL1100/LL1200 first, and then reinstall LL1100/LL1200.

■ Installing LL1100/LL1200 Parameter Setting Software

Operating procedures and screens in Windows Vista

1. Start Windows.

2. Insert the CD of LL1100 or LL1200 into the CD-ROM drive. The start-up screen appears automatically.



Note: If the start-up screen does not appear automatically and the **AutoPlay** screen appears, click **Run startup.exe** to display the start-up screen.

3. Click **LL1100 Installation** or **LL1200 Installation**.

4. To continue, follow the message given in each dialog box.

■ Verifying Installation

From the **Start** menu of Windows, point to **All Programs**, then **Green Series** and verify that the **Green Series** contains **Green Series LL1100** or **Green Series LL1200**.

■ Uninstalling LL1100/LL1200

From the **Start** menu of Windows, select **Control Panel > Programs and Features** (*1) > **LL1100** or **LL1200** and uninstall it.


In Windows Vista, the User Account Control screen appears. Click **Allow**. The LL1100 or LL1200 is uninstalled.

*1: From the **Start** menu of Windows, select **Control Panel > Uninstall a program** if the control panel's display method is "Control Panel Home." In Windows XP, **Add or Remove Programs**.


Connecting Controller to Personal Computer (for USB interface)

Follow the procedure below to connect the controller to a personal computer.

- 1.Connect the dedicated adapter to the USB communication port of a personal computer using the dedicated cable.
- 2.As shown in Figure 4, hand the dedicated adapter from the top groove of the controller.
- 3.Push the adapter to the controller's front panel to securely fix it in place.



- **Make sure the dedicated adapter is attached to the controller in a vertical orientation. Communication is not possible if the dedicated adapter is attached in a slanting position.**
- **Do not remove the dedicated cable (for USB interface) while LL1100/LL1200 communicate, or it may affect the stability of the operation system.**
- **Do not suspend while LL1100/LL1200 communicate, or the system may fail to recover subsequently form the suspension.**



Trademarks:

- Windows XP, Windows Vista, and Windows 7 are registered trademarks of Microsoft Corporation, USA.
- Pentium is a registered trademark of Intel Corporation, USA.
- Ethernet is a registered trademark of XEROX Corporation, USA.
- Other company and product names are trademarks or registered trademarks of their respective holders.

YOKOGAWA

YOKOGAWA ELECTRIC CORPORATION
Network Solutions Business Division
2-9-32, Naka-cho Musashino-shi, Tokyo 180-8750 JAPAN

YOKOGAWA CORPORATION OF AMERICA
Head office and for product sales
2 Dart Road, Newnan, Georgia 30265, USA

YOKOGAWA EUROPE B.V.
Headquarters
Euroweg 2, 3825 HD Amersfoort, THE NETHERLANDS

www.yokogawa.com/ns